■ NetApp

Invite and remove users

Astra

Ben Cammett, Erika Barcott January 22, 2021

Table of Contents

Invite and remove users	 1
Invite users	 •
Change a user's role	 •
Remove users	 •

Invite and remove users

Invite users to join your Astra account and remove users that should no longer have access to the account.

Invite users

Account Owners and Admins can invite other users to join the Astra account.

Steps

- 1. Make sure that the user has a Cloud Central login.
- 2. Click Account.
- 3. In the Users tab, click + Invite users.
- Enter the user's name, email address, and their role.

Note the following:

- The email address must match the email address that the user used to sign up to Cloud Central.
- Each role provides the following permissions:
 - An Owner has Admin permissions and can delete accounts.
 - An **Admin** has Member permissions and can invite other users.
 - A Member can fully manage apps and compute.
 - A Viewer can view resources.

5. Click Send invite(s).

Result

The user will receive an email that invites them to join your account.

Change a user's role

An Account Owner can change the role of all users, while an Account Admin can change the role of users who have the Admin, Member, or Viewer role.

Steps

- 1. Click Account.
- 2. In the **Users** tab, select the drop-down list in the **Role** column for the user.
- 3. Select a new role and then click **Change Role** when prompted.

Result

Astra updates the user's permissions based on the new role that you selected.

Remove users

An Account Owner can remove other users from the account at any time.

Steps

- 1. Click Account.
- 2. In the **Users** tab, select the users that you want to remove.
- 3. Click Actions and select Remove user/s.
- 4. When you're prompted, confirm deletion by typing the user's name and then click **Yes, Remove User**.

Result

Astra removes the user from the account.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP "AS IS" AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.